Data acquisition with the ADS1115 on the raspberry PI

Generated by Doxygen 1.8.17

1 rpi_ads1115	1
2 Class Index	3
2.1 Class List	3
3 Class Documentation	5
3.1 ADS1115rpi Class Reference	5
3.1.1 Detailed Description	5
3.1.2 Member Function Documentation	5
3.1.2.1 hasSample()	5
3.1.2.2 setChannel()	6
3.1.2.3 start()	6
3.2 ADS1115settings Struct Reference	6
3.2.1 Detailed Description	7
Index	9

Chapter 1

rpi_ads1115

Raspberry PI C++ library for the ADS1115

github: https://github.com/berndporr/rpi_ads1115

2 rpi_ads1115

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

ADS1115rpi	
This class reads data from the ADS1115 in the background (separate thread) and calls a callback	
function whenever data is available	5
ADS1115settings	
ADS1115 initial settings when starting the device	6

4 Class Index

Chapter 3

Class Documentation

3.1 ADS1115rpi Class Reference

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

```
#include <ads1115rpi.h>
```

Public Member Functions

• ~ADS1115rpi ()

Destructor which makes sure the data acquisition stops on exit.

• virtual void hasSample (float sample)=0

Called when a new sample is available.

void setChannel (ADS1115settings::Input channel)

Selects a different channel at the multiplexer while running.

void start (ADS1115settings settings=ADS1115settings())

Starts the data acquisition in the background and the callback is called with new samples.

• void stop ()

Stops the data acquistion.

3.1.1 Detailed Description

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

3.1.2 Member Function Documentation

3.1.2.1 hasSample()

Called when a new sample is available.

This needs to be implemented in a derived class by the client. Defined as abstract.

6 Class Documentation

Parameters

sample	Voltage from the selected channel.
--------	------------------------------------

3.1.2.2 setChannel()

Selects a different channel at the multiplexer while running.

Call this in the callback handler hasSample() to cycle through different channels.

Parameters

channel Sets the channel from A

3.1.2.3 start()

Starts the data acquisition in the background and the callback is called with new samples.

Parameters

settings	A struct with the settings.

The documentation for this class was generated from the following file:

• ads1115rpi.h

3.2 ADS1115settings Struct Reference

ADS1115 initial settings when starting the device.

```
#include <ads1115rpi.h>
```

Public Types

```
enum SamplingRates {
    FS8HZ = 0, FS16HZ = 1, FS32HZ = 2, FS64HZ = 3,
    FS128HZ = 4, FS250HZ = 5, FS475HZ = 6, FS860HZ = 7 }
    Sampling rates.
enum PGA { FSR2_048 = 2, FSR1_024 = 3, FSR0_512 = 4, FSR0_256 = 5 }
    Full scale range: 2.048V, 1.024V, 0.512V or 0.256V.
enum Input { AIN0 = 0, AIN1 = 1, AIN2 = 2, AIN3 = 3 }
    Channel indices.
```

Public Attributes

```
• int i2c bus = 1
```

I2C bus used (99% always set to one)

• uint8 t address = DEFAULT ADS1115 ADDRESS

I2C address of the ads1115.

SamplingRates samplingRate = FS8HZ

Sampling rate requested.

PGA pgaGain = FSR2_048

Requested full scale range.

• Input channel = AIN0

Requested input channel (AIN0..AIN3)

• bool initPIGPIO = true

If set to true the pigpio will be initialised.

• int drdy_gpio = DEFAULT_ALERT_RDY_TO_GPIO

GPIO pin connected to ALERT/RDY.

3.2.1 Detailed Description

ADS1115 initial settings when starting the device.

The documentation for this struct was generated from the following file:

• ads1115rpi.h

8 Class Documentation

Index

```
ADS1115rpi, 5
hasSample, 5
setChannel, 6
start, 6
ADS1115settings, 6
hasSample
ADS1115rpi, 5
setChannel
ADS1115rpi, 6
start
ADS1115rpi, 6
```